

Getting Started


Get started with the Machine Control Toolkit by building a simple machine interface (step-by-step instructions below).

1. Open up a blank LabVIEW VI




2. Place the buffer template from the Machine Control Toolkit onto your block diagram.


The buffer template contains the general machine control logic and the case control on the front panel are added, and then enter the case structure contained by your machine until you stop the program. Moving to the template is a control to turn on a G-Code command.



3. To create a simple machine control interface with X, Y, and Z jogging commands, place 6 buttons on your front panel and name them accordingly.




4. On the block diagram, add a case structure inside the buffer template while loop.




5. Connect the case selector to the x1 control button. From the Machine Control Toolkit, add the Jog x1 VI inside the case structure.



6. Create a control for the jogging step size as you can adjust it from the front panel. Wire the feedback into the feedback input using a local variable, and connect the G-Code String Out to the Write Buffer also using a local variable.




7. Repeat for the other 5 directions (X, +X, Y, -Y, Z).




8. Add control over the machine's units.

First, add another case structure, and create a control on the front panel. Wire that control to the case selector, and connect the feedback to the feedback input using a local variable. Then create a case structure for the units and wire it to the feedback input using a local variable. Wire that to the feedback input using a local variable.



9. Go to your front panel, and select the port your machine is plugged into and your feedback, and run the VI.



10. This will now be able to jog your machine in all directions, and control the step size and units!